



TMcraft Shell API Function Manual

Original Instructions

Software version: 1.20.1000

Document version: 1.0

Release date: 2024-11-01

This Manual contains information of the Techman Robot product series (hereinafter referred to as the TM AI Cobot). The information contained herein is the property of Techman Robot Inc. (hereinafter referred to as the Corporation) and shall not be reproduced in whole or in part without prior authorization from the Corporation. No information contained herein shall be considered an offer or commitment. The information herein is subject to change without notice. The document is periodically reviewed and revised. The Corporation assumes no responsibility for any errors or omissions in the documentation.



 and  logos are registered trademark of TECHMAN ROBOT INC. in Taiwan and other countries and the company reserves the ownership of this manual and its copy and its copyrights.

Table of Content

Manual Revision History	6
API Revision History	6
1. Overview.....	8
2. Programming with TMcraft Shell API	10
3. TMcraft API functions (Shell related)	12
3.1 TMcraftShellAPI.....	12
3.1.1 Version	12
3.1.2 CloseShellConnection	12
3.1.3 GetErrMsg.....	12
3.1.4 InitialTMcraftShell.....	13
3.2 EndButtonEventProvider	13
3.2.1 HasEndButtonEventOwnership.....	13
3.2.2 IsEndButtonBoardcastMode	14
3.2.3 ReleaseEndButtonEventOwnership	14
3.2.4 SetEndButtonEventOwnership.....	14
3.2.5 EndButtonClickEvent	15
3.3 FreebotProvider	15
3.3.1 GetFreeBot	15
3.3.2 HoldFreeBotKeyToHandGuide	15
3.3.3 KeepFreeBot.....	16
3.3.4 SetFreeBot.....	16
3.4 IOProvider	16
3.4.1 GetAllIOData	16
3.4.2 ReadAnalogInput	17
3.4.3 ReadAnalogOutput.....	17
3.4.4 ReadDigitInput	18
3.4.5 ReadDigitOutput	19
3.4.6 SetCameraLight	19
3.4.7 WriteAnalogOutput.....	20
3.4.8 WriteDigitOutput.....	20
3.5 ProjectRunProvider	21
3.5.1 GetCurrentProject	21
3.5.2 GetDisplayBoardInfo	21
3.5.3 GetProjectList	22
3.5.4 PauseProject.....	22
3.5.5 RunProject	22
3.5.6 SetCurrentProject.....	23
3.5.7 StopProject	23
3.6 RobotJogProvider	23

3.6.1 HoldPlayKeyToRun	24
3.6.2 JogByBase	24
3.6.3 JogByJoint	25
3.6.4 JogCircle	25
3.6.5 JogRelativeByBase	26
3.6.6 JogRelativeByJoint.....	27
3.6.7 JogRelativeByTool.....	28
3.6.8 KeepJogging	28
3.6.9 StopJog.....	28
3.7 RobotStatusProvider	29
3.7.1 GetCurrentBaseName.....	29
3.7.2 GetCurrentPayload	29
3.7.3 GetCurrentPoseByCurrentBase	30
3.7.4 GetCurrentPoseByJointAngle	30
3.7.5 GetCurrentPoseByRobotBase	30
3.7.6 GetCurrentRobotConfigs.....	31
3.7.7 GetCurrentSpeedPercentage.....	31
3.7.8 GetCurrentTcp.....	31
3.7.9 GetCurrentToolSpeed	32
3.7.10 GetFlowVersion.....	32
3.7.11 GetOperationMode.....	32
3.7.12 GetRobotModelType	33
3.7.13 GetRobotName	33
3.7.14 ProjectEditOrNot	33
3.7.15 ProjectPauseOrNot	34
3.7.16 ProjectRunOrNot.....	34
3.7.17 RobotErrorOrNot	34
3.7.18 RobotEstopOrNot.....	35
3.7.19 SetCurrentBase.....	35
3.7.20 SetCurrentPayload.....	35
3.7.21 SetCurrentTcp	36
3.7.22 ErrorEvent.....	36
3.8 RobotStickProvider	36
3.8.1 RobotStickStatus.....	36
3.8.2 RobotVirtualStickKeyEvent	37
3.9 ScriptProjectProvider	37
3.9.1 DeleteScriptProject	37
3.9.2 GetScriptProjectList	37
3.9.3 NewScriptProject.....	38
3.9.4 OpenScriptProject	38

3.9.5 ReadScriptProjectContent.....	38
3.9.6 ReadScriptProjectRemark.....	39
3.9.7 SaveScriptProject.....	39
3.9.8 WriteScriptProjectContent.....	40
3.9.9 WriteScriptProjectRemark.....	40
3.10 SystemProvider	40
3.10.1 ExportGlobalVariable	40
3.10.2 ExportLog.....	41
3.10.3 ExportProject	41
3.10.4 ExportTCP	41
3.10.5 GetControl.....	42
3.10.6 GetCurrentLanguageCulture.....	42
3.10.7 GetDateTime.....	42
3.10.8 GetSupportTimeZoneList	43
3.10.9 GetTimeZone	43
3.10.10 GetTMflowType	44
3.10.11 ImportGlobalVariable	44
3.10.12 ImportProject.....	44
3.10.13 ImportTCP.....	45
3.10.14 LogIn	45
3.10.15 LogOut	46
3.10.16 SetDateTime	46
3.10.17 SetTimeZone.....	46
3.10.18 ShowTMflow	47
3.10.19 Shutdown	47
3.11 TCPProvider	47
3.11.1 ChangeTcplnertia	48
3.11.2 ChangeTcpMass.....	48
3.11.3 ChangeTcpMassCenter	48
3.11.4 ChangeTcpPose	49
3.11.5 CreateNewTcp.....	49
3.11.6 DeleteTcp	49
3.11.7 GetProjectVisionTcpList.....	50
3.11.8 GetTcplnertia	50
3.11.9 GetTcpList	51
3.11.10 GetTcpMass	51
3.11.11 GetTcpMassCenter.....	51
3.11.12 IsTcpExist	52
3.12 TextFileProvider	52
3.12.1 DeleteTextFile	52

3.12.2 ExportTextFile	52
3.12.3 GetTextFileList	53
3.12.4 ImportTextFile	53
3.12.5 NewTextFile	53
3.12.6 ReadTextFile	54
3.12.7 WriteTextFile	54
3.13 VariableProvider	54
3.13.1 ChangeGlobalVariableValue	55
3.13.2 ChangeVariableRuntimeValue	55
3.13.3 CreateGlobalVariable	55
3.13.4 DeleteGlobalVariable	56
3.13.5 GetGlobalVariableList	56
3.13.6 GetGlobalVariableValue	56
3.13.7 GetVariableRuntimeValue	57
3.13.8 IsGlobalVariableExist	57
4. Enumeration types	58
4.1 FreeBotMode	58
4.2 IO_TYPE	58
4.3 LogExportSetting	59
4.4 MoveMode	59
4.5 RobotEventType	60
4.6 TMcraftErr	60
4.7 TMflowType	61
4.8 VariableType	61
4.9 VirtualKeyEvent	62
5. Additional class	64
5.1 DeviceIOInfo	64
5.2 DigitIOInfo	64
5.3 ErrorStatus	65
5.4 FreeBotInfo	66
5.5 TCPInfo	66
5.6 VariableInfo	67

Manual Revision History

Revision	Date	Revised Content
1.0	2024-11-01	Original release

API Revision History

Version	Date	Change Note/History
1.14.1200	2023/8	<ul style="list-style-type: none"> ● 1st release
1.16.1400	2024/2	<ul style="list-style-type: none"> ● [Add] class TMcraftShellAPI ● [Add] class TMcraftToolbarAPI ● [Add] interface ITMcraftToolbarEntry ● [Add] class ErrorStatus ● [Add] FreeBotInfo.MoveMode ● [Add] class MoveMode ● [Add] class LogExportSetting ● [Add] RobotEventType.EndButtonFreeBotChanged
1.18.1400	2024/6	<ul style="list-style-type: none"> ● [Add] class TMcraftSetupAPI ● [Add] class TMcraftNodeAPI.TextfileProvider ● [Add] class TMcraftShellAPI.TextfileProvider ● [Add] class TMcraftToolbarAPI.TextfileProvider ● [Add] TMcraftShellAPI.ProjectRunProvider.GetProjectList ● [Add] TMcraftShellAPI.RobotStatusProvider.GetRobotName ● [Add] TMcraftNodeAPI.RobotStatusProvider.GetRobotModelType ● [Add] TMcraftNodeAPI.RobotStatusProvider.GetFlowVersion
1.20.1100	2024/11	<ul style="list-style-type: none"> ● [Add] TMcraftNodeType.dll ● [Add] class TMcraftNodeAPI.FreeBotProvider ● [Add] class TMcraftNodeAPI.EndButtonEventProvider ● [Deprecated] TMcraftNodeAPI.RobotStatusProvider.GetFreeBot ● [Deprecated] TMcraftNodeAPI.RobotStatusProvider.SetFreeBot ● [Deprecated] TMcraftNodeAPI.RobotStatusProvider.EndButtonClickEvent ● [Add] class TMcraftShellAPI.FreeBotProvider ● [Add] class TMcraftShellAPI.EndButtonEventProvider ● [Deprecated] TMcraftShellAPI.RobotStatusProvider.GetFreeBot ● [Deprecated] TMcraftShellAPI.RobotStatusProvider.SetFreeBot ● [Deprecated] TMcraftShellAPI.RobotStatusProvider.EndButtonClickEvent ● [Add] class TMcraftToolbarAPI.FreeBotProvider ● [Add] class TMcraftToolbarAPI.EndButtonEventProvider ● [Deprecated] TMcraftToolbarAPI.RobotStatusProvider.GetFreeBot ● [Deprecated] TMcraftToolbarAPI.RobotStatusProvider.SetFreeBot

		<ul style="list-style-type: none">● [Deprecaded] TMcraftToolbarAPI.RobotStatusProvider.EndButton-ClickEvent● [Add] class TMcraftSetupAPI.FreeBotProvider● [Add] class TMcraftSetupAPI.EndButtonEventProvider● [Deprecaded] TMcraftSetupAPI.RobotStatusProvider.GetFreeBot● [Deprecaded] TMcraftSetupAPI.RobotStatusProvider.SetFreeBot● [Deprecaded] TMcraftSetupAPI.RobotStatusProvider.EndButtonClickEvent
--	--	---

1. Overview

Developers can now develop a full-page customized GUI (Graphical User Interface) based on C#/WPF, which is overlay above TMflow; this kind of custom plugin is called TMcraft Shell. Since end-users might not interact much with TMflow, allowing developers fully shape the user experience. TMcraft Shell can serve as a setup wizard, a dashboard, or both. For instance, it's possible to create a Palletizing Operator with it.

- Wizard:

Using the Wizard UI, users can easily configure settings like box size, pallet size, and layer structure. Once confirmed, the TMcraft Shell program collects these parameters and creates the relevant script project.

- Dashboard:

As the application begins, the robot executes the previously mentioned script project. The TMcraft Shell program then retrieves various robot data or project variable values, displaying them on the Dashboard. Users can also view palletizing throughput matrixes like Units per Hour, Overall Equipment Efficiency, Defect Count, and Downtime.




Figure 1: Architecture of TMcraft Shell

Plugins	Node	Shell	Toolbar	Setup
Base (Add/Edit/Delete)	✓			✓
Point (Add/Edit/Delete)	✓			✓
Tool (Add/Edit/Delete)	✓	✓	✓	✓
Digital IO (Read/Write)	✓	✓	✓	✓
Analog IO (Read/Write)	✓	✓	✓	✓

capabilities \ Plugins	Node	Shell	Toolbar	Setup
Project Variables (New/Edit)	✓	✓	✓	✓
Global Variables (New/Edit)	✓	✓	✓	✓
Vision Job (Add/Open/Delete)	✓			
Jog the robot	✓	✓	✓	
Freebot (Set/Get)	✓	✓	✓	✓
End Button Event	✓	✓	✓	✓
Get Current Language	✓	✓	✓	✓
Get TMflow Type	✓	✓	✓	✓
Text file (Read/Write)	✓	✓	✓	✓
TMscript on flow project (Read/Write)	✓			✓
Login/Logout/Get Control		✓		
script Project (Add/Edit/Delete)		✓		
Robot status (Error, Run, etc.)		✓	✓	
Error Event		✓	✓	
Virtual Robot Stick		✓		
Export/Import		✓		
Variables Runtime Value (Read/Write)		✓	Read only	

Table 1: A brief overview of the capabilities of various TMcraft plugin APIs

Developers must use the TMcraft Packer from the TMcraft Development Kit to package the TMcraft Shell exe file and its associated files before importing them into TMflow.




Figure 2: Development process of a TMcraft Shell

This manual briefly explains the framework of a TMcraft Shell Program and outlines all TMcraft Shell API functions. Note that this manual does not cover all enums and additional classes in the TMcraft.dll, but the most relevant to TMcraft Shell.

2. Programming with TMcraft Shell API

To understand the TMcraft Shell program structure, refer the sample code below.

`using TMcraft;`

```
namespace TMcraftSample
{
    public partial class MainWindow : Window
    {
        TMcraftShellAPI ShellUI;

        public MainWindow ()
        {
            InitializeComponent();

            private void Window_Loaded (object sender, RoutedEventArgs e)
            {
                if (ShellUI == null)
                {
                    ShellUI = new TMcraftShellAPI();
                    ShellUI.InitialTMcraftShell();
                }
            }

            private void Window_Unloaded (object sender, RoutedEventArgs e) {}

            private void Window_Closing (object sender, System.ComponentModel.CancelEventArgs e)
            {
                if (ShellUI != null) ShellUI.CloseShellConnection();
            }

            private void Btn_ShowTMflow_Click (object sender, RoutedEventArgs e)
            {
                //example : using TMcraft Shell API function to show TMflow and hide the Shell GUI
                if(ShellUI != null) ShellUI.SystemProvider.ShowTMflow();
            }
        }
    }
}
```

To create the foundation of a TMcraft Shell Program, please remind the following items:

1. Include TMcraft.dll as a reference. Remember to import the namespace (`using TMcraft`) onto

the program.

2. Declare a global object based on the class `TMcraftShellAPI`.
3. When loading the window of the Shell GUI, assign the object (`new TMcraftShellAPI()`), then call the function `InitialTMcraftShell()`.
4. When closing the window of the Shell GUI, remember to call the function `ShellUI.CloseShell-Connection()`.

The rest of the Program should be all sorts of event functions that can interact with TMflow through TMcraft functions.

3. TMcraft API functions (Shell related)

3.1 TMcraftShellAPI

TMcraft.dll is a combination of the APIs of all sort of TMcraft items; for TMcraft Shell, please declare an object of the class *TMcraftShellAPI* and use the function within. Like other TMcraft API, *TMcraftShellAPI* contains different members (or providers) functions in order to interact with TMflow, such as creating Project variables or jogging the robot, etc.



IMPORTANT:

TM AI + AOI Edge comes without any robot-related functionality, so it does not support some TMcraft API functions. For TMcraft Shell, the unsupported functions include:

- RobotJogProvider: all functions
- RobotStatusProvider: all functions, except GetFlowVersion, GetOperationMode, ProjectEditOrNot, ProjectPauseOrNot, ProjectRunOrNot, and ErrorEvent
- RobotStickProvider: all functions
- SystemProvider: ExportTCP
- TCPProvider: all functions
- Enumeration types: FreeBotMode, MoveMode, RobotEventType, VirtualKeyEvent
- Additional class: FreeBotInfo, TCPInfo

3.1.1 Version

Syntax

string *TMcraftShellAPI*.Version

Description

A member of the *TMcraftShellAPI* class. Returns a *string* represents the version of the current TMcraft.dll and is read-only.

Return

string Version of the current TMcraft API

3.1.2 CloseShellConnection

Syntax

void *CloseShellConnection* ()

Description

Closes the connection between TMcraft Shell and TMflow.

Parameters

errorCode	The <i>unit</i> error code returned by most Provider functions.
errorMessage	Response the associated error message by the input error code.

Return

None.

3.1.3 GetErrMsg

Syntax

```
TMcraft.TMcraftErr GetErrMsg(
    unit errorCode,
    out string ErrorMessage
)
```

Description

Output the error message according to the error code input. This function is used for checking the result of calling Provider functions.

Parameters

errorCode	The unit error code returned by most Provider functions.
errorMessage	Response the associated error message by the input error code.

Return

[TMcraft.TMcraftErr](#) Returns [TMcraftErr.OK](#) if the function works properly; otherwise, returns the corresponding TMcraftErr. For more detail, please check [enum TMcraft.TMcraftErr](#).

3.1.4 InitialTMcraftShell

Syntax

```
TMcraft.TMcraftErr InitialTMcraftShell()
```

Description

Start the connection between TMcraft Shell and TMflow.

Parameters

No parameters are required.

Return

[TMcraft.TMcraftErr](#) Returns [TMcraftErr.OK](#) if the function works properly; otherwise, returns the corresponding TMcraftErr. For more detail, please check [enum TMcraft.TMcraftErr](#).

3.2 EndButtonEventProvider

[EndButtonEventProvider](#) contains functions related to the end button event.

3.2.1 HasEndButtonEventOwnership

Syntax

```
uint HasEndButtonEventOwnership()
```

Description

TMcraft plugin can call this function to check if it has the end button event owner-

ship or not. If yes, this TMcraft plugin is the only one who can receive the end button event signal.

Parameters

None

Return

bool

Returns True if the TMcraft plugin has the end button event ownership; otherwise, returns Fail.

3.2.2 IsEndButtonBoardcastMode

Syntax

uint IsEndButtonBoardcastMode()

Description

TMcraft plugin can call this function to check if the end button event is currently in boardcast mode. If yes, that means all TMcraft plugins can receive the event signal; otherwise, one of the TMcraft plugin has the ownership. i.e. other plugins receive no signal from the event.

Parameters

None

Return

bool

Returns True if the end button event is currently in boardcast mode; otherwise, returns Fail.

3.2.3 ReleaseEndButtonEventOwnership

Syntax

uint ReleaseEndButtonEventOwnership()

Description

TMcraft plugin can call this function to release the button event ownership.

Parameters

None

Return

uint

The error code that represents the result of the function calling.

3.2.4 SetEndButtonEventOwnership

Syntax

uint SetEndButtonEventOwnership()

Description

TMcraft plugin can call this function to get the end button event ownership.

Parameters

None

Return`uint`

The error code that represents the result of the function calling.

3.2.5 EndButtonClickEvent**Description**

An event type denotes to the click event occurred on the buttons of the End Module. Function can be linked to this event so that it will be activated once the event is triggered.

3.3 FreebotProvider

`FreeBotProvider` provides functions related to freebot.

3.3.1 GetFreeBot**Syntax**

```
uint GetFreeBot(
    out FreeBotInfo freeBot
)
```

Description

Gets the value of the current FreeBot settings.

Parameters

<code>freeBot</code>	Value of the current FreeBot settings defined by <code>FreeBotInfo</code> .
----------------------	---

Return`uint`

The error code that represents the result of the function calling.

3.3.2 HoldFreeBotKeyToHandGuide**Syntax**

```
uint HoldFreeBotKeyToHandGuide(
    bool holdKey
)
```

Description

Mimics holding the freebot button to enter hand guide mode. Note that, calling this function alone is not enough, another function `KeepFreeBot` should be running at the same time.

Parameters

<code>holdKey</code>	True means to activate the hand guide mode; false means to deactivate.
----------------------	--

Return

`uint`

The error code that represents the result of the function calling.

3.3.3 KeepFreeBot

Syntax

```
uint KeepFreeBot()
```

Description

Keep the current hand guide mode. After sending HoldFreeBotKeyToHandGuide, this function should be keep sending every 100 - 500 ms until the hand guiding ends, otherwise, the robot will leave hand guide mode.

Parameters

None

Return

`uint`

The error code that represents the result of the function calling.

3.3.4 SetFreeBot

Syntax

```
uint SetFreeBot(
    FreeBotInfo freeBot
)
```

Description

Sets FreeBot settings.

Parameters

`freeBot`

A FreeBotInfo being assigned as FreeBot settings.

Return

`uint`

The error code that represents the result of the function calling.

3.4 IOProvider

`IOProvider` provides functions for TMcraft item to interact with system I/O.

3.4.1 GetAllIOData

Syntax

```
uint GetAllIOData(
    out List<DeviceIOInfo> ioData
)
```

Description

Gets all IO status.

Parameters

	ioData	A List of DeviceIOInfo objects that denotes all IO status data.
Return	uint	The error code that represents the result of the function calling.

3.4.2 ReadAnalogInput

Syntax

```
uint ReadAnalogInput(
    IO_TYPE type,
    int deviceSerialNum,
    int channelNum,
    out float value
)
```

Description

Read the status of a specific Analog Input.

Parameters

type	The IO_TYPE enum that defines which device the target Analog Input belongs to.
deviceSerialNum	Device serial number, which always starts from 0 and is more meaningful if the target device is an external IO module because there might be multiple external IO module devices within the system. The number is 0 if the target device is the Control box IO board or end module IO board because there are only one Control box IO board and one end module IO board.
channelNum	Channel number.
value	Analog Input value, ranged from -10V to 10V.

Return

uint	The error code that represents the result of the function calling.
------	--

3.4.3 ReadAnalogOutput

Syntax

```
uint ReadAnalogOutput(
    IO_TYPE type,
    int deviceSerialNum,
    int channelNum,
    out float value
)
```

Description

Read the status of a specific Analog Output.

Parameters

type	The <code>IO_TYPE</code> enum that defines which device the target Analog Outputs belongs to.
deviceSerialNum	Device serial number, which always starts from 0 and is more meaningful if the target device is an external IO module because there might be multiple external IO module devices within the system. The number is 0 if the target device is the Control box IO board or end module IO board because there are only one Control box IO board and one end module IO board.
channelNum	Channel number.
value	Analog Outputs value, ranged from -10V to 10V.

Return

<code>uint</code>	The error code that represents the result of the function calling.
-------------------	--

3.4.4 ReadDigitInput

Syntax

```
uint ReadDigitInput(
    IO_TYPE type,
    int deviceSerialNum,
    int channelNum,
    out bool status
)
```

Description

Read the status of a specific Digital Input.

Parameters

type	The <code>IO_TYPE</code> enum that defines which device the target Digital Input belongs to.
deviceSerialNum	Device serial number, which always starts from 0 and is more meaningful if the target device is an external IO module because there might be multiple external IO module devices within the system. The number is 0 if the target device is the Control box IO board or end module IO board because there are only one Control box IO board and one end module IO board.
channelNum	Channel number.
status	Digital Input status, where <code>bool</code> true is HIGH and <code>bool</code> false is LOW.

Return`uint`

The error code that represents the result of the function calling.

3.4.5 ReadDigitOutput**Syntax**

```
uint ReadDigitOutput(
    IO_TYPE type,
    int deviceSerialNum,
    int channelNum,
    out bool status
)
```

Description

Read the status of a specific Digital Output.

Parameters

<code>type</code>	The <code>IO_TYPE</code> enum that defines which device the target Digital Outputs belongs to.
<code>deviceSerialNum</code>	Device serial number, which always starts from 0 and is more meaningful if the target device is an external IO module because there might be multiple external IO module devices within the system. The number is 0 if the target device is the Control box IO board or end module IO board because there are only one Control box IO board and one end module IO board.
<code>channelNum</code>	Channel number.
<code>status</code>	Digital Outputs status, where <code>bool</code> true is HIGH and <code>bool</code> false is LOW.

Return`uint`

The error code that represents the result of the function calling.

3.4.6 SetCameraLight**Syntax**

```
uint SetCameraLight(
    bool status
)
```

Description

Switch the Eye-In-Hand camera light to the ON or OFF status.

Parameters

<code>status</code>	<code>bool</code> true denotes turning the light ON,
---------------------	--

`bool` false denotes turning the light OFF

Return

`uint` The error code that represents the result of the function calling.

3.4.7 WriteAnalogOutput

Syntax

```
uint WriteAnalogOutput(
    IO_TYPE type,
    int deviceSerialNum,
    int channelNum,
    float value
)
```

Description

Set the value of a specific Analog Output.

Parameters

<code>type</code>	The <code>IO_TYPE</code> enum that defines which device the target Analog Outputs belongs to.
<code>deviceSerialNum</code>	Device serial number, which always starts from 0 and is more meaningful if the target device is an external IO module because there might be multiple external IO module devices within the system. The number is 0 if the target device is the Control box IO board or end module IO board because there are only one Control box IO board and one end module IO board.
<code>channelNum</code>	Channel number.
<code>value</code>	Analog Outputs value, ranged from -10V to 10V.

Return

`uint` The error code that represents the result of the function calling.

3.4.8 WriteDigitOutput

Syntax

```
uint WriteDigitOutput(
    IO_TYPE type,
    int deviceSerialNum,
    int channelNum,
    bool status
)
```

Description

Change the status of a specific Digital Output.

Parameters

type	The <code>IO_TYPE</code> enum that defines which device the target Digital Outputs belongs to.
deviceSerialNum	Device serial number, which always starts from 0 and is more meaningful if the target device is an external IO module because there might be multiple external IO module devices within the system. The number is always 0 if the target device is the Control box IO board or end module IO board because there are only one Control box IO board and one end module IO board.
channelNum	Signal channel number.
status	Digital Outputs status, where <code>bool</code> true is HIGH and <code>bool</code> false is LOW.

Return

<code>uint</code>	The error code that represents the result of the function calling.
-------------------	--

3.5 ProjectRunProvider

`ProjectRunProvider` provides functions related to project run.

3.5.1 GetCurrentProject

Syntax

```
uint GetCurrentProject(
    out string projectName
)
```

Description

Get the name of the current project.

Parameters

projectName	Name of the project created.
-------------	------------------------------

Return

<code>uint</code>	The error code that represents the result of the function calling.
-------------------	--

3.5.2 GetDisplayBoardInfo

Syntax

```
uint GetDisplayBoardInfo(
    out string info
)
```

Description

Outputs the content currently shown on TMflow Display Board.

Parameters

info	Outputs the current Display Board Content with the following format: [{ <i>Background color</i> },{ <i>Font color</i> },{ <i>Tilte</i> },{ <i>Content</i> }].
------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.5.3 GetProjectList

Syntax

```
uint GetProjectList(
    out List<string> projectInfo
)
```

Description

Get the list of projects of the current system.

Parameters

projectInfo	List of projects (names) of the current system.
-------------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.5.4 PauseProject

Syntax

```
uint PauseProject()
```

Description

Pause the current running project. To continue the project run, use RunProject().

Parameters

No parameters are required.

Return

uint	The error code that represents the result of the function calling.
------	--

3.5.5 RunProject

Syntax

```
uint RunProject()
```

Description

Run the current project.

Parameters

No parameters are required.

Return

uint The error code that represents the result of the function calling.

3.5.6 SetCurrentProject**Syntax**

```
uint SetCurrentProject(
    string projectName
)
```

Description

Given a project name, set it as the current project. Note that this function can only be used during Auto mode.

Parameters

projectName Name of the project to be the current project.

Return

uint The error code that represents the result of the function calling.

3.5.7 StopProject**Syntax**

```
uint StopProject()
```

Description

Stop the current project.

Parameters

No parameters are required.

Return

uint The error code that represents the result of the function calling.

3.6 RobotJogProvider

RobotJogProvider provides functions for TMcraft item to jog the robot.

**IMPORTANT:**

If the TMcraft Shell uses any RobotJogProvider functions for motion control, it is the responsibility of the developer to make sure single point of control within ISO 10218-1.

3.6.1 HoldPlayKeyToRun

Syntax

```
uint HoldPlayKeyToRun(
    bool holdKey
)
```

Description

This function mimics the process of holding play key to start jogging motion. Note that, at the same time, **KeepJogging()** should be sent every 100 - 500 ms until the jogging ends, otherwise, the jogging will stop automatically.

Parameters

holdKey	True means to hold the key; false means to release the key.
---------	---

3.6.2 JogByBase

Syntax

```
uint JogByBase(
    float speedPercentage,
    float [] targetCoordinates
)
```

Description

Jogs the robot towards the target's Coordinates (relative to current base and tool) with a 6×1 **float** array {x, y, z, rx, ry ,rz}. This function will not trigger any motion directly, as it requires following by either pressing the PLAY button on the robot stick (may also requires Enabling Switch) or using API functions: **HoldPlayKeyToRun** + **KeepJogging**.

Parameters

speedPercentage	Speed percentage is equivalent to the speed (in percentage) setting on the TMflow Controller, where the current jogging speed should match the max joint speed. The max joint speed of the robot model is multiplied by the speed percentage, and the product (TCP speed) of this multiplication should always be lower than Manual Control mode speed limit (250 mm/s). speedPercentage is expressed in decimals (e.g., 1.5 for 1.5%)..
targetMovementValue	A 6×1 float array {x, y, z, rx, ry ,rz} of target movement value.

Return

`uint`

The error code that represents the result of the function calling.

3.6.3 JogByJoint

Syntax

```
uint JogByJoint(
    float speedPercentage,
    float[] targetJointAngles
)
```

Description

Jogs the robot towards the targets Joint Angles. This function will not trigger any motion directly, as it requires following by either pressing the PLAY button on the robot stick (may also requires Enabling Switch) or using API functions:

HoldPlayKeyToRun + KeepJogging.

Parameters

<code>speedPercentage</code>	Speed percentage is equivalent to the speed (in percentage) setting on the TMflow Controller, where the current jogging speed should match the max joint speed. The max joint speed of the robot model is multiplied by the speed percentage, and the product (TCP speed) of this multiplication should always be lower than Manual Control mode speed limit (250 mm/s). <code>speedPercentage</code> is expressed in decimals (e.g., 1.5 for 1.5%).
<code>targetJointAngles</code>	A 6×1 <code>float</code> array {J1, J2, J3, J4, J5, J6} which represents the target Joint Angle.

Return

`uint`

The error code that represents the result of the function calling.

3.6.4 JogCircle

Syntax

```
uint JogCircle(
    float speedPercentage,
    float[] passPoint,
    float[] endPoint,
    int targetAngle
)
```

Description

Jogs the end-effector circularly. Like circle node, the circle is always defined by 3 points: the initial position of the end-effector, a pass point and an end point. This function will not trigger any motion directly, as it requires following by either pressing the PLAY button on the robot stick (may also requires Enabling Switch) or using API functions: **HoldPlayKeyToRun** + **KeepJogging**.

Parameters

speedPercentage	Speed percentage is equivalent to the speed (in percentage) setting on the TMflow Controller, where the current jogging speed should match the max joint speed. The max joint speed of the robot model is multiplied by the speed percentage, and the product (TCP speed) of this multiplication should always be lower than Manual Control mode speed limit (250 mm/s). speedPercentage is expressed in decimals (e.g., 1.5 for 1.5%).
passPoint	The 2nd point required to define the circle, described by Cartesian Space.
endpoint	The last point required to define the circle, described by Cartesian Space.
targetAngle	Define how much arc of the circle to be jogged. If the target angle is 0, the trajectory will end at the end point.

Return

uint	The error code that represents the result of the function calling.
------	--

3.6.5 JogRelativeByBase

Syntax

```
uint JogRelativeByBase(
    float speedPercentage,
    float [] targetCoordinates
)
```

Description

Jogs the robot by relative motion according to the current base. This function will not trigger any motion directly, as it requires following by either pressing the PLAY button on the robot stick (may also requires Enabling Switch) or using API functions: **HoldPlayKeyToRun** + **KeepJogging**.

Parameters

speedPercentage	Speed percentage is equivalent to the speed (in percentage) setting on the TMflow Controller, where the current jogging
-----------------	---

speed should match the max joint speed. The max joint speed of the robot model is multiplied by the speed percentage, and the product (TCP speed) of this multiplication should always be lower than Manual Control mode speed limit (250 mm/s). speedPercentage is expressed in decimals (e.g., 1.5 for 1.5%).

targetCoordinates A 6×1 **float** array {x, y, z, rx, ry ,rz} of target movement value.

Return

uint The error code that represents the result of the function calling.

3.6.6 JogRelativeByJoint

Syntax

```
uint JogRelativeByJoint(
    float speedPercentage,
    float [] targetJointAngles
)
```

Description

Jogs the robot relatively by given joint angles along with Tool Axes. This function will not trigger any motion directly, as it requires following by either pressing the PLAY button on the robot stick (may also requires Enabling Switch) or using API functions: **HoldPlayKeyToRun** + **KeepJogging**.

Parameters

speedPercentage Speed percentage is equivalent to the speed (in percentage) setting on the TMflow Controller, where the current jogging speed should match the max joint speed. The max joint speed of the robot model is multiplied by the speed percentage, and the product (TCP speed) of this multiplication should always be lower than Manual Control mode speed limit (250 mm/s). speedPercentage is expressed in decimals (e.g., 1.5 for 1.5%).

targetJointAngles A 6×1 **float** array {J1, J2, J3, J4, J5, J6} of target movement value.

Return

uint The error code that represents the result of the function calling.

3.6.7 JogRelativeByTool

Syntax

```
uint JogRelativeByTool(
    float speedPercentage,
    float [] targetMovementValue
)
```

Description

Jogs the robot along with Tool Axes. Remind that, like using TMflow Controller, users need to use the robot stick (e.g. Enabling Device + PLAY) to start the motion.

Parameters

speedPercentage	Speed percentage is equivalent to the speed (in percentage) setting on the TMflow Controller, where the current jogging speed should match the max joint speed. The max joint speed of the robot model is multiplied by the speed percentage, and the product (TCP speed) of this multiplication should always be lower than Manual Control mode speed limit (250 mm/s). speedPercentage is expressed in decimals (e.g., 1.5 for 1.5%).
targetMovementValue	A 6×1 float array {x, y, z, rx, ry ,rz} of target movement value.

Return

uint	The error code that represents the result of the function calling.
-------------	--

3.6.8 KeepJogging

Syntax

```
uint KeepJogging()
```

Description

Keep the current jogging. After sending HoldPlayKeyToRun, this function should be keep sending every 100 - 500 ms until the jogging ends, otherwise, the jogging will stop automatically.

Parameters

No parameters are required.

Return

uint	The error code that represents the result of the function calling.
-------------	--

3.6.9 StopJog

Syntax

```
uint StopJog()
```

Description

Stops all Jog motion immediately. It is also recommended to call this function before calling Jog motion functions in order to clear the motion buffer

Parameters

No parameters are required.

Return

uint The error code that represents the result of the function calling.

3.7 RobotStatusProvider

RobotStatusProvider provides functions for TMcraft items to access different robot status information.

3.7.1 GetCurrentBaseName**Syntax**

```
uint GetCurrentBaseName(
    out string baseName
)
```

Description

Gets the name of the current Base.

Parameters

baseName Current Base name.

Return

uint The error code that represents the result of the function calling.

3.7.2 GetCurrentPayload**Syntax**

```
uint GetCurrentPayload(
    out float payload
)
```

Description

Gets the current payload value set to the robot (end-effector).

Parameters

payload Current payload value being assigned.

Return

uint The error code that represents the result of the function calling.

3.7.3 GetCurrentPoseByCurrentBase

Syntax

```
uint GetCurrentPoseByCurrentBase(
    out float[] currentPose
)
```

Description

Gets robot current TCP position defined by the Current Base.

Parameters

currentPose	A 6×1 float array {x, y, z, rx, ry, rz} that denotes the current robot pose.
-------------	---

Return

uint	The error code that represents the result of the function calling.
-------------	--

3.7.4 GetCurrentPoseByJointAngle

Syntax

```
uint GetCurrentPoseByJointAngle(
    out float[] jointAngles
)
```

Description

Gets all robot current Joint Angles.

Parameters

jointAngles	A 6×1 float array {j1, j2, j3, j4, j5, j6} that denotes the current robot pose.
-------------	--

Return

uint	The error code that represents the result of the function calling.
-------------	--

3.7.5 GetCurrentPoseByRobotBase

Syntax

```
uint GetCurrentPoseByRobotBase(
    out float[] currentPose
)
```

Description

Gets robot current TCP position defined by the Robot Base.

Parameters

currentPose	A 6×1 float array {x, y, z, rx, ry, rz} that denotes the current robot pose.
-------------	---

Return`uint`

The error code that represents the result of the function calling.

3.7.6 GetCurrentRobotConfigs**Syntax**

```
uint GetCurrentRobotConfigs(
    out int[] robotConfigs
)
```

Description

Gets current Robot Config.

Parameters

<code>robotConfigs</code>	A 3×1 interger array denoting the robot configurations of the point; here is the definition: <code>int[0]</code> : 0 – Right Arm, 1 – Left Arm <code>int[1]</code> : 2 – Above Elbow, 3 – Below Elbow <code>int[2]</code> : 4 – Up Wrist, 5 – Down Wrist
---------------------------	---

Return`uint`

The error code that represents the result of the function calling.

3.7.7 GetCurrentSpeedPercentage**Syntax**

```
uint GetCurrentSpeedPercentage(
    out int speedPercentage
)
```

Description

Gets current speed percentage setting.

Parameters

<code>speedPercentage</code>	Current speed percentage setting.
------------------------------	-----------------------------------

Return`uint`

The error code that represents the result of the function calling.

3.7.8 GetCurrentTcp**Syntax**

```
uint GetCurrentTcp(
    out string tcpName
)
```

Description

Gets the name of current TCP.

Parameters

tcpName	Current TCP name.
---------	-------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.9 GetCurrentToolSpeed

Syntax

```
uint GetCurrentToolSpeed(
    out string speed
)
```

Description

Gets the current tool speed.

Parameters

speed	Current Tool speed.
-------	---------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.10 GetFlowVersion

Syntax

```
uint GetFlowVersion(
    out string result
)
```

Description

Gets the version of TMflow.

Parameters

result	TMflow version.
--------	-----------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.11 GetOperationMode

Syntax

```
uint GetOperationMode(
    out int mode
)
```

Description

Gets current operation mode.

Parameters

mode	Current operation mode, which includes: 0 – Manual and 1 – Auto.
------	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.12 GetRobotModelType

Syntax

```
uint GetRobotModelType(
    out string result
)
```

Description

Gets the model type of the robot.

Parameters

result	Model Type of the robot.
--------	--------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.13 GetRobotName

Syntax

```
uint GetRobotName(
    out string robotName
)
```

Description

Gets the name of the robot

Parameters

robotName	Name of the robot.
-----------	--------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.14 ProjectEditOrNot

Syntax

```
uint ProjectEditOrNot(
    out bool result
)
```

Description

Outputs if any project is under editing or not.

Parameters

result	If any project is under editing or not.
--------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.15 ProjectPauseOrNot

Syntax

```
uint ProjectPauseOrNot(
    out bool result
)
```

Description

Outputs if the current project is paused or not.

Parameters

result	If the current project is paused or not. It would be True only if there is a running project and it is in pause status.
--------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.16 ProjectRunOrNot

Syntax

```
uint ProjectRunOrNot(
    out bool result
)
```

Description

Outputs if any project is running or not.

Parameters

result	If any project is running or not.
--------	-----------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.17 RobotErrorOrNot

Syntax

```
uint RobotErrorOrNot(
    out bool result
)
```

Description

Outputs if the robot is in error status or not.

Parameters

result	If the robot is in error status or not.
--------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.18 RobotEstopOrNot

Syntax

```
uint RobotEstopOrNot(
    out bool result
)
```

Description

Outputs if the robot is under Estop status or not.

Parameters

result	If the robot is under editing or not.
--------	---------------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.19 SetCurrentBase

Syntax

```
uint SetCurrentBase(
    string baseName
)
```

Description

Assigns a specific Base as the current base.

Parameters

baseName	Name of the base being assigned.
----------	----------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.20 SetCurrentPayload

Syntax

```
uint SetCurrentPayload(
    float payload
)
```

Description

Sets a payload value to the robot (end-effector).

Parameters

	payload	Payload value being assigned.
Return	uint	The error code that represents the result of the function calling.

3.7.21 SetCurrentTcp

Syntax

```
uint SetCurrentTcp(
    string tcpName
)
```

Description

Assigns a specific TCP as the current TCP.

Parameters

tcpName	Name of the TCP being assigned.
---------	---------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.7.22 ErrorEvent

Description

An event type denotes to the error event occurred on the robot. Function can be linked to this event so that it will be activated once the event is triggered.

3.8 RobotStickProvider

[RobotStickProvider](#) provides functions for developing a virtual robot stick on TMcraft Shell.

3.8.1 RobotStickStatus

Syntax

```
uint RobotStickStatus(
    out bool status
)
```

Description

Denotes if the robot stick is either in local control or remote control. For more details, please refer to the Safety Manual.

Parameters

status	True means robot stick is in local control; false means robot stick is in remote control.
--------	---

Return

uint The error code that represents the result of the function calling.

3.8.2 RobotVirtualStickKeyEvent

Syntax

```
uint RobotVirtualStickEvent(  
    TMcraft.VirtualKeyEvent event  
)
```

Description

Trigger a robot stick signal according to the input parameter.

Parameters

event	Robot stick signal. For more detail, please check the TMcraft enum VirtualKeyEvent .
-------	--

Return

uint The error code that represents the result of the function calling.

3.9 ScriptProjectProvider

[ScriptProjectProvider](#) provides functions for managing script projects, including creating new projects, retrieving existing ones, listing projects, and writing script projects.

3.9.1 DeleteScriptProject

Syntax

```
uint DeleteScriptProject(  
    string projectName  
)
```

Description

Delete a specific script project.

Parameters

projectName	Name of the project to be deleted.
-------------	------------------------------------

Return

uint The error code that represents the result of the function calling.

3.9.2 GetScriptProjectList

Syntax

```
uint GetScriptProjectList(  
    ref List<string[]> projectsInfo  
)
```

Description

Get the list of script project, along with information.

Parameters

projectsInfo	A list of string arrays represents all script projects within the robot. Each array contains the following information of a script project: [<i>Project Name, Build date, Last updated date, Initial speed percentage, Project Type, Last execution date</i>] .
--------------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.9.3 NewScriptProject

Syntax

```
uint NewScriptProject(
    string projectName
)
```

Description

Create a new script project.

Parameters

projectName	Name of the project to be created.
-------------	------------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.9.4 OpenScriptProject

Syntax

```
uint OpenScriptProject (
    string projectName
)
```

Description

Open a specific script project

Parameters

projectName	Name of the project to be opened.
-------------	-----------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.9.5 ReadScriptProjectContent

Syntax

```
uint ReadScriptProjectContent(
```

```
        out string projectContent
    )
```

Description

Read the content of the opened script project.

Parameters

projectContent	Content of the opened script project.
----------------	---------------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.9.6 ReadScriptProjectRemark

Syntax

```
uint ReadScriptProjectRemark(
    string projectName,
    out string projectRemark
)
```

Description

Read the remark of a specific script project. Note that it is available to read or write the remark only if that project is not opened currently. Project remark is a kind of editable information stored within a script project.

Parameters

projectName	Name of the script project to be read.
projectRemark	Project remark Outputs as a string.

Return

uint	The error code that represents the result of the function calling.
------	--

3.9.7 SaveScriptProject

Syntax

```
uint SaveScriptProject(
    string projectName
)
```

Description

Save the opened script project with the given project name.

Parameters

projectName	Name of the project to be saved.
-------------	----------------------------------

Return

uint The error code that represents the result of the function calling.

3.9.8 WriteScriptProjectContent

Syntax

```
uint WriteScriptProjectContent(
    string projectContent
)
```

Description

Replace the content of the opened script project with a new one.

Parameters

projectContent Content to be written onto the opened script project.

Return

uint The error code that represents the result of the function calling.

3.9.9 WriteScriptProjectRemark

Syntax

```
uint WriteScriptProjectRemark(
    string projectName,
    string projectRemark
)
```

Description

Replace the remark of a specific script project with the new one. Note that it is available to read or write the remark only if that project is not opened currently. Project remark is a kind of editable information stored within a script project.

Parameters

projectName Name of the target script project.
projectRemark Project remark Outputs as a string.

Return

uint The error code that represents the result of the function calling.

3.10 SystemProvider

SystemProvider provides functions for TMcraft item to interact with TMflow System Settings.

3.10.1 ExportGlobalVariable

Syntax

```
uint ExportGlobalVariable(
```

```
        string varName
    )
```

Description

Export a specific global variable to the flash drive.

Parameters

varName	Name of the global variable to be exported.
---------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.2 ExportLog

Syntax

```
uint ExportLog(
    TMcraft.LogExportSetting logSetting
)
```

Description

Export the log of the robot to the flash drive.

Parameters

logSetting	Log setting defined the amount of log to be exported. For more detail, please check the TMcraft enum: LogExportSetting .
------------	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.3 ExportProject

Syntax

```
uint ExportProject(
    string projectName
)
```

Description

Export a specific project to the flash drive.

Parameters

projectName	Name of the project to be exported.
-------------	-------------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.4 ExportTCP

Syntax

```
uint ExportTCP(
    string tcpName
)
```

Description

Export a specific tcp to the flash drive.

Parameters

tcpName	Name of the tcp to be exported.
---------	---------------------------------

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.5 GetControl

Syntax

```
uint GetControl(
    bool get
)
```

Description

Get or release control of the robot.

Parameters

get	True means get control; false means release control.
-----	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.6 GetCurrentLanguageCulture

Syntax

```
uint GetCurrentLanguageCulture(
    out string language
)
```

Description

Gets the current language setting of the system.

Parameters

language	Current System language, e.g., en-US, zh-TW, zh-CN, ja-JP, de-DE, ko-KR
----------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.7 GetDateTime

Syntax

```
uint GetDateTime(
    out System.DateTimeOffset dateTimeOffset
)
```

Description

Get the date and time of TMflow system.

Parameters

dateTimeOffset	Outputs a DateTimeOffset type, represents the current date and time of the TMflow system
----------------	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.8 GetSupportTimeZoneList

Syntax

```
uint GetSupportTimeZoneList(
    out List<System.TimeZoneInfo> timeZoneInfos
)
```

Description

Get the time zone list of TMflow system.

Parameters

dateTimeOffset	Outputs a List of TimeZoneInfo type, represents the time zones supported by the TMflow system.
----------------	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.9 GetTimeZone

Syntax

```
uint GetTimeZone(
    out string ID,
    out bool IsAutoAdjustDST,
)
```

Description

Get the date and time of TMflow system.

Parameters

ID	Time zone identifier
IsAutoAdjustDST	True means TMflow will automatically adjust the clock for daylight saving changes. Note that this parameter is significant if and only if that time zones support daylight saving time.

Return`uint`

The error code that represents the result of the function calling.

3.10.10 GetTMflowType

Syntax

```
uint GetTMflowType(
    out TMflowType type
)
```

Description

Gets the current TMflow type of the system.

Parameters

<code>type</code>	Represent the TMflow type (e.g. Robot, AOIEdge, etc.) of the current system. For more detail, check the description of enum TMflowType.
-------------------	---

Return`uint`

The error code that represents the result of the function calling.

3.10.11 ImportGlobalVariable

Syntax

```
uint ImportGlobalVariable(
    string robotName,
    string varName
)
```

Description

Import a specific global variable to the robot.

Parameters

<code>robotName</code>	Name of the folder where the system can find the item to be imported.
<code>varName</code>	Name of the global variable to be imported.

Return`uint`

The error code that represents the result of the function calling.

3.10.12 ImportProject

Syntax

```
uint ImportProject(
    string robotName,
```

```
        string projectName
    )
```

Description

Import a specific project to the robot

Parameters

robotName	Name of the folder where the system can find the item to be imported.
projectName	Name of the project to be imported.

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.13 ImportTCP

Syntax

```
uint ImportTCP(
    string robotName,
    string tcpName
)
```

Description

Import a specific tcp to the robot.

Parameters

robotName	Name of the folder where the system can find the item to be imported.
tcpName	Name of the tcp to be imported.

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.14 LogIn

Syntax

```
uint LogIn(
    string userName,
    string password
)
```

Description

Login with the give user name and password.

Parameters

userName	User name to login the robot.
password	Password that belongs to the user name.

Return

`uint`

The error code that represents the result of the function calling.

3.10.15 LogOut

Syntax

```
uint LogOut()
```

Description

Logout the robot.

Parameters

No parameters are required.

Return

`uint`

The error code that represents the result of the function calling.

3.10.16 SetDateTime

Syntax

```
uint SetDateTime(
    unit year,
    unit month,
    unit day,
    unit hour,
    unit minute,
    unit second
)
```

Description

Set the date and time of TMflow system.

Parameters

year	Year
month	Month
day	Day
hour	Hour
minute	Minute
second	Second

Return

`uint`

The error code that represents the result of the function calling.

3.10.17 SetTimeZone

Syntax

```
uint SetTimeZone(
```

```

        string ID,
        bool IsAutoAdjustDST
    )

```

Description

Set the date and time of TMflow system.

Parameters

ID	Time zone identifier
IsAutoAdjustDST	True means TMflow will automatically adjust the clock for daylight saving changes. Note that this parameter is significant if and only if that time zones support daylight saving time.

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.18 ShowTMflow**Syntax**

```
uint ShowTMflow()
```

Description

Hide TMcraft Shell and show TMflow GUI temporary. User can click the Back to Shell Button on TMflow (left upper corner) and back to TMcraft Shell.

Parameters

No parameters are required.

Return

uint	The error code that represents the result of the function calling.
------	--

3.10.19 Shutdown**Syntax**

```
uint Shutdown()
```

Description

Shut down the robot.

Parameters

No parameters are required.

Return

uint	The error code that represents the result of the function calling.
------	--

3.11 TCPProvider

TCPProvider provides functions for TMcraft to access or modify TCPs with the robot.

3.11.1 ChangeTcpInertia

Syntax

```

UInt ChangeTcpInertia(
    string tcpName,
    float[] inertiaValue
)

```

Description

Modifies the inertia value of a specific TCP.

Parameters

tcpName	Name of the target TCP.
inertiaValue	A 3×1 float array {lxx, lyy, lzz} of inertia value being assigned.

Return

UInt	The error code that represents the result of the function calling.
-------------	--

3.11.2 ChangeTcpMass

Syntax

```

UInt ChangeTcpMass(
    string tcpName,
    float mass
)

```

Description

Modifies the mass value (kg) of a specific TCP.

Parameters

tcpName	Name of the target TCP.
mass	Mass value (kg) to be assigned.

Return

UInt	The error code that represents the result of the function calling.
-------------	--

3.11.3 ChangeTcpMassCenter

Syntax

```

UInt ChangeTcpMassCenter(
    string tcpName,
    float[] massCenter
)

```

Description

Modifies the Mass Center value of a specific TCP.

Parameters

tcpName	Name of the target TCP.
massCenter	A 6×1 float array {x, y, z, rx, ry, rz} that denotes the location of the mass center of the TCP.

Return

Uint	The error code that represents the result of the function calling.
-------------	--

3.11.4 ChangeTcpPose

Syntax

```
Uint ChangeTcpPose(
    string tcpName,
    float[] toolCenterPoint
)
```

Description

Modifies the tool center point of a specific TCP by a 6×1 **float** array {x, y, z, rx, ry, rz} referring to Flange Base.

Parameters

tcpName	Name of the target TCP being modified.
toolCenterPoint	A 6×1 float array[6] {x, y, z, rx, ry, rz} of new Pose value referring to Flange Base.

Return

Uint	The error code that represents the result of the function calling.
-------------	--

3.11.5 CreateNewTcp

Syntax

```
Uint CreateNewTcp(
    TCPInfo tcpData
)
```

Description

Create a new TCP by using a **TCPInfo** Type as input.

Parameters

tcpData	TCPInfo type assigned for the new TCP.
---------	--

Return

Uint	The error code that represents the result of the function calling.
-------------	--

3.11.6 DeleteTcp

Syntax

```

    Uint DeleteTcp(
        string tcpName
    )

```

Description

Delete a specific TCP file.

Parameters

tcpName	Name of the TCP being deleted.
---------	--------------------------------

Return

Uint	The error code that represents the result of the function calling.
------	--

3.11.7 GetProjectVisionTcpList

Syntax

```

    Uint GetProjectVisionTcpList(
        out List<string> visionTcpList
    )

```

Description

Gets the list of Vision TCP Names from the current Project.

Parameters

visionTcpList	A List of vision TCP names.
---------------	-----------------------------

Return

Uint	The error code that represents the result of the function calling.
------	--

3.11.8 GetTcpInertia

Syntax

```

    Uint GetTcpInertia(
        string tcpName,
        out float[] inertiaValue
    )

```

Description

Gets the inertia value of a specific TCP.

Parameters

tcpName	Name of the target TCP.
inertiaValue	A 3x1 float array {lxx, lyy, lzz} that denotes the inertia value of the target TCP.

Return

Uint	The error code that represents the result of the function calling.
------	--

3.11.9 GetTcpList

Syntax

```

    Uint GetTcpList(
        out List<TCPInfo> tcpList
    )

```

Description

Gets the list of all TCPs (with data) within the robot.

Parameters

tcpList	A List of TCPInfo type that denotes all TCPs within the robot.
---------	--

Return

Uint	The error code that represents the result of the function calling.
------	--

3.11.10 GetTcpMass

Syntax

```

    Uint GetTcpMass(
        string tcpName,
        out float mass
    )

```

Description

Gets the value of mass (kg) from a specific TCP.

Parameters

tcpName	Name of the target TCP.
mass	Mass value (kg) of the target TCP.

Return

Uint	The error code that represents the result of the function calling.
------	--

3.11.11 GetTcpMassCenter

Syntax

```

    Uint GetTcpMassCenter(
        string tcpName,
        out float[] massCenter
    )

```

Description

Gets the Mass Center value of a specific TCP.

Parameters

tcpName	Name of the target TCP.
massCenter	A 6×1 float array {x, y, z, rx, ry, rz} that denotes the location of the mass center of the TCP.

Return**UInt**

The error code that represents the result of the function calling.

3.11.12 IsTcpExist**Syntax**

```
bool IsTcpExist(
    string tcpName
)
```

Description

Checks if a specific tcp exists or not.

Parameters

tcpName	Name of the tcp being checked.
---------	--------------------------------

Return**bool**

True if exists, false if not.

3.12 TextFileProvider**TextFileProvider** provides functions for TMcraft plugin to manipulate Textfiles within TMflow.**3.12.1 DeleteTextFile****Syntax**

```
uint DeleteTextFile (
    string fileName
)
```

Description

Deletes a specific Textfile.

Parameters

fileName	Name of the file being deleted.
----------	---------------------------------

Return**uint**

The error code that represents the result of the function calling.

3.12.2 ExportTextFile**Syntax**

```
uint ExportTextFile (
    string fileName
)
```

Description

Exports a specific Textfile to the USB.

Parameters

	fileName	Name of the file being exported.
Return	uint	The error code that represents the result of the function calling.

3.12.3 GetTextFileList

Syntax

```
uint GetTextFileList (
    out string list
)
```

Description

Gets the list of Textfile names within the current system.

Parameters

list	A list of Textfile names within the current system
------	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.12.4 ImportTextFile

Syntax

```
uint ImportTextFile (
    string robotName,
    string fileName
)
```

Description

Import a Textfile to the robot.

Parameters

robotName	Name of the folder where the system can find the item to be imported.
fileName	Name of the file being imported.

Return

uint	The error code that represents the result of the function calling.
------	--

3.12.5 NewTextFile

Syntax

```
uint NewTextFile (
    string filename,
    string fileContent
)
```

Description

Create a new Textfile.

Parameters

fileName	Name of the file being created.
fileContent	Content of the Textfile to be assigned.

Return

uint	The error code that represents the result of the function calling.
------	--

3.12.6 ReadTextFile**Syntax**

```
uint ReadTextFile (
    string filename,
    out string fileContent
)
```

Description

Read the content of a specific Textfile.

Parameters

fileName	Name of the file being read.
fileContent	Content of the Textfile to be read.

Return

uint	The error code that represents the result of the function calling.
------	--

3.12.7 WriteTextFile**Syntax**

```
uint WriteTextFile (
    string filename,
    string fileContent
)
```

Description

Write content to a specific Textfile.

Parameters

fileName	Name of the file being written.
fileContent	Content of the Textfile to be written.

Return

uint	The error code that represents the result of the function calling.
------	--

3.13 VariableProvider

VariableProvider provides functions for TMcraft to access or modify the variables of the robot.

3.13.1 ChangeGlobalVariableValue

Syntax

```
uint ChangeGlobalVariableValue(
    List<string[]> value
)
```

Description

Sets the value of a specific Global Variables.

Parameters

value	A list of global variables being modified; each element within this list should be a 2×1 string array {varName, varValue}, where varName is the name of the target variable and varValue is the value being assigned.
-------	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.13.2 ChangeVariableRuntimeValue

Syntax

```
uint ChangeVariableRuntimeValue(
    string varName,
    string value
)
```

Description

Changes the runtime value of a specific variable.

Parameters

varName	Represents the name of the variable to be changed.
value	Represents the value to be assigned.

Return

uint	The error code that represents the result of the function calling.
------	--

3.13.3 CreateGlobalVariable

Syntax

```
uint CreateGlobalVariable(
    string name,
    VariableType type,
    string value
)
```


)

Description

Creates a new global variable by the input parameters.

Parameters

name	Name of the variable being created.
type	Type of variable being created.
value	Value being assigned to the new variable.

Return

uint	The error code that represents the result of the function calling.
------	--

3.13.4 DeleteGlobalVariable**Syntax**

```
uint DeleteGlobalVariable(
    string name
)
```

Description

Deletes a specific global variable from the robot.

Parameters

name	Name of the global variable being deleted.
------	--

Return

uint	The error code that represents the result of the function calling.
------	--

3.13.5 GetGlobalVariableList**Syntax**

```
uint GetGlobalVariableList(
    ref List<VariableInfo>variables
)
```

Description

Gets all Global Variables ([VariableInfo](#) Type) from the robot and overwrites the input [List](#).

Parameters

variables	A List of Variable Info type that contains all global variables within the robot.
-----------	---

Return

uint	The error code that represents the result of the function calling.
------	--

3.13.6 GetGlobalVariableValue

Syntax

```
uint GetGlobalVariableValue(
    string varName,
    out string value
)
```

Description

Gets the value of a specific global variable.

Parameters

varName	Represents the name of the target global variable.
value	Outputs the value of {varName}

Return

uint	The error code that represents the result of the function calling.
------	--

3.13.7 GetVariableRuntimeValue**Syntax**

```
uint GetVariableRuntimeValue(
    string varName,
    out string value
)
```

Description

Gets the runtime value of a specific variable.

Parameters

varName	Represents the name of the target variable.
value	Outputs the value of {varName}

Return

uint	The error code that represents the result of the function calling.
------	--

3.13.8 IsGlobalVariableExist**Syntax**

```
bool IsGlobalVariableExist(
    string varName
)
```

Description

Checks if a specific Global Variable exists or not.

Parameters

varName	Name of the Global Variable being checked.
---------	--

Return

bool	True if exists, false if not.
------	-------------------------------

4. Enumeration types

4.1 FreeBotMode

```
public enum FreeBotMode
{
    All_Joints,
    Custom,
    RXYZ,
    SCARA_Like,
    XYZ
}
```

Description

Enum [FreeBotMode](#), which is used as a member of the class [TMcraftShellAPI.FreeBotInfo](#) and represents the FreeBot mode setting.

Items

FreeBotMode.All_Joints	Represents free all joints mode.
FreeBotMode.Custom	Represents custom FreeBot mode.
FreeBotMode.RXYZ	Represents free RXYZ (Rx, Ry, Rz) mode.
FreeBotMode.SCARA_Like	Represents SCARA-like FreeBot mode.
FreeBotMode.XYZ	Represents free XYZ mode.

4.2 IO_TYPE

```
public enum IO_TYPE
{
    UNKNOWN,
    CONTROL_BOX,
    END_MODULE,
    EXT_MODULE
}
```

Description

Enum [IO_TYPE](#), paired with [TMcraftShellAPI.IOProvider](#) functions such as [WriteDigitOutput\(\)](#), defines the IO device within TM robot.

Items

IO_TYPE.UNKNOWN	Represents an unknown device detected. When using IOProvider.GetAllIOData() , if there is any unknown device detected, IO_TYPE.UNKNOWN will be found within the DeviceIOInfo data
IO_TYPE.CONTROL_BOX	Control Box I/O.
IO_TYPE.END_MODULE	End Module I/O (Tool End I/O Interface).
IO_TYPE.EXT_MODULE	External I/O Device(s) connected to the robot.

4.3 LogExportSetting

```
public enum LogExportSetting
{
    Today,
    _3days,
    _7days,
    14_days,
    All
}
```

Description

Enum [LogExportSetting](#), which is used as the input parameter of the function [TMCraftShellAPI.SystemProvider.ExportLog](#), represents the amount of log to be exported.

Items

LogExportSetting.Today	Represents to export the log for today.
LogExportSetting._3days	Represents to export the log for the past 3 days.
LogExportSetting._7days	Represents to export the log for the past 7 days.
LogExportSetting._14days	Represents to export the log for the past 14 days.
LogExportSetting.All	Represents to export all log within the robot.

4.4 MoveMode

```
public enum MoveMode
{
    Accurate,
    Fast,
    Nromal
}
```

Description

Enum [MoveMode](#), which is used as one of the parameter of the class [TMCraftShellAPI.FreeBotInfo](#). Move Mode is for users to adjust the initial damping of joints with modes of Accurate, Normal, and Fast. Damping increases the hand guide weight allowing faster stoppage while releasing the FREE button. For easier dragging, joint damping decreases proportionally as TCP speed increases during the hand guide. Once damping drops to zero, it stays at zero until the FREE button is released

Items

MoveMode.Accurate	The highest joint damping. For the high initial force requirement with fast stoppage while releasing the FREE button.
MoveMode.Fast	The zero joint damping. For the low initial force requirement for dragging.

MoveMode.Normal

The low joint damping. For the medium initial force requirement with reasonable accuracy while stopping.

4.5 RobotEventType

```
public enum RobotEventType
{
    EndButtonFreeBotChanged,
    EndButtonGripperChanged,
    EndButtonPointChanged,
    EndButtonVisionChanged
}
```

Description

Enum [RobotEventType](#), paired with [TMcraftShellAPI.RobotStatusProvider](#)'s event [EndButtonClickEvent](#), defines the click event occurred on the buttons of the End Module.

Items

EndButtonFreeBotChanged	Represents the click event of the Free Button on the End Module. True denotes FreeBot is triggered while False denotes that the Free Button is either released or over-pressed.
EndButtonGripperChanged	Represents the click event of the Gripper Button on the End Module. True denotes the button is pressed while False denotes that pressing is released.
EndButtonPointChanged	Represents the click event of the Point Button on the End Module. True denotes the button is pressed while False denotes that pressing is released.
EndButtonVisionChanged	Represents the click event of the Vision Button on the End Module. True denotes the button is pressed while False denotes that pressing is released.

4.6 TMcraftErr

```
public enum TMcraftErr
{
    ConnectionFail,
    DevResponseError,
    ExceptionError
    InvalidParameter,
    NodeCloseFail,
    OK
}
```

Description

Enum [TMcraftErr](#) represents the possible error that may occurred not from TMflow, but TMcraft API itself. TMcraftErr is used as the object type returned by the functions [TMcraftShellAPI.GetErrMsg](#) and [TMcraftShellAPI.InitialTMcraftShell](#).

Items

TMcraftErr.ConnectionFail	TMcraft API failed to connect with TMflow.
TMcraftErr.DevResponseError	Unexpected error on TMcraft API. Please contact Techman Inc. for further analysis.
TMcraftErr.ExceptionError	Exception happened on TMCraft API. Please contact Techman Inc. for further analysis.
TMcraftErr.InvalidParameter	TMcraft API detects invalid parameters when calling provider functions. For example, empty string or incorrect array size.
TMcraftErr.NodeCloseFail	Failure happened when closing TMcraft Node on TMflow.
TMcraftErr.OK	No error.

4.7 TMflowType

```
public enum TMflowType
```

```
{
    AOIEdge,
    Client,
    OLP,
    Robot,
    Unknown
}
```

Description

Enum [TMflowType](#), which is the Outputs of [TMcraftShellAPI.SystemProvider.GetTMflowType](#) and represent the TMflow type of the current system, or more specifically, of where the [GetTMflowType](#) function is called.

Items

TMflowType.AOIEdge	Represents that the current system is AOI Edge.
TMflowType.Client	Represents that the current system is client TMflow.
TMflowType.OLP	Represents that the current system is TMstudio Pro.
TMflowType.Robot	Represents that the current system is on the robot.
TMflowType.Unknown	Represents that the current system is not recognizable as one of the TMflow type.

4.8 VariableType

```
public enum VariableType
```

```
{
    Integer,
    Float,
    Double,
    String,
    Byte,
    Boolean,
    IntegrArray,
    FloatArray,
    DoubleArray,
```

```

    StringArray,
    ByteArray,
    BooleanArray,
    Null
}

```

Description

Enum [VariableType](#), paired with [TMcraftShellAPI.VariableProvider](#) function [CreateGlobalVariable\(\)](#), defines variable types on TMflow.

4.9 VirtualKeyEvent

```

public enum VirtualKeyEvent
{
    MAKey,
    MALongKey,
    MinusKey,
    MinusLongKey,
    PauseKey,
    PauseLongKey,
    PlayKey,
    PlayLongKey,
    PlusKey,
    PlusLongKey,
    StopKey,
    StopLongKey
}

```

Description

Enum [VirtualKeyEvent](#), which is used as the parameter of the function [RobotStickProvider.RobotVirtualStickKeyEvent](#).

Items

VirtualKeyEvent.MAKey	Represents a single press signal of MA (change mode) Button.
VirtualKeyEvent.MALongKey	Represents a long press signal of MA (change mode) Button.
VirtualKeyEvent.MinusKey	Represents a single press signal of Minus Button.
VirtualKeyEvent.MinusLongKey	Represents a long press signal of Minus Button.
VirtualKeyEvent.PauseKey	Represents a single press signal of Pause Button.
VirtualKeyEvent.PauseLongKey	Represents a long press signal of Pause Button.
VirtualKeyEvent.PlayKey	Represents a single press signal of Play Button.
VirtualKeyEvent.PlayLongKey	Represents a long press signal of Play Button.
VirtualKeyEvent.PlusKey	Represents a single press signal of Plus Button.
VirtualKeyEvent.PlusLongKey	Represents a long press signal of Plus Button.
VirtualKeyEvent.StopKey	Represents a single press signal of Stop Button.
VirtualKeyEvent.StopLongKey	Represents a long press signal of Stop Button.

5. Additional class

5.1 DeviceIOInfo

```
public class DeviceIOInfo
{
    public IO_TYPE type;
    public int deviceSerialNum;
    public List<DigitIOInfo> DICollection;
    public List<DigitIOInfo> DOCollection;
    public List<float> AOCollection;
    public List<float> AICollection;
}
```

Description

The [TMcraftShellAPI.DeviceIOInfo](#) describes all sorts of information related to a specific IO Device of the robot.

Members

Type	IO device that this information describes.
deviceSerialNum	Device serial number, which always starts from 0 and is more meaningful if the target device is an external IO module because there might be multiple external IO module devices within the system. The number is 0 if the target device is the Control box IO board or end module IO board because there is always one Control box IO board and one end module IO board.
DICollection	A List of DigitIOInfo Type, which represents all Digital Inputs within the IO Device and should be empty if there are no Digital Inputs. Please note that the index of the list represents the channel number.
DOCollection	A List of DigitIOInfo Type that represents all Digital Outputs within the IO Device and should be empty if there are no Digital Outputs. Please note that the index of the list represents the channel number.
AOCollection	A List of float Type that represents all Analog Outputs within the IO Device and should be empty if there are no Analog Outputs. Please note that the index of the list represents the channel number.
AICollection	A List of float Type that represents all Analog Inputs within the IO Device and should be empty if there are no Analog Inputs. Please note that the index of the list represents the channel number.

5.2 DigitIOInfo

```
public class DigitIOInfo
{
    public bool value;
    public bool isUserDefined;
}
```

Description

[DigitIOInfo](#) describes the information of a Digital I/O channel which is used as the [List](#) data type of [TMcraftShellAPI.DeviceIOInfo.DICollection](#) and [TMcraftShellAPI.DeviceIO-Info.DICollection](#).

Members

value	True denotes HIGH while false denotes LOW.
isUserDefined	True denotes this Digital Channel is set as a User-Defined IO (that triggers a signal to a button of the Robot Stick, reads the signal from a stick button, or detects if an error occurs in the system).

5.3 ErrorStatus

```
public class ErrorStatus
{
    public uint Error_Code;
    public uint[] Error_Codes;
    public string Error_Time;
    public uint Last_Error_Code;
    public uint[] Last_Error_Codes;
    public uint Last_Error_Time;
}
```

Description

[ErrorStatus](#) denotes the structure of the data return by [TMcraftShellAPI.ErrorEvent](#). Note that the [ErrorEvent](#) does not return this object type directly, but a json string instead that can be converted to the [ErrorStatus](#) type.

Members

Error_Code	The major error code of the current error event, which should be the first item of Error_Codes , i.e. Error_Codes[0] . Note that Error_Code would be cleared after reset.
Error_Codes	All error codes related to the current error event. Note that Error_Codes would be cleared after reset.
Error_Time	Time stamp of Error_Code .
Last_Error_Code	The major error code of the last error event recorded, which should be the first item of Last_Error_Codes , i.e. Last_Error_Codes[0] . Note that Last_Error_Code would not be cleared after reset, but would be refreshed when another error event happens.
Last_Error_Codes	All error codes related to the last error event. Note that Last_Error_Codes would not be cleared after reset, but would be refreshed when another error event happens.
Last_Error_Time	Time stamp of Last_Error_Code .

5.4 FreeBotInfo

```
public class FreeBotInfo
{
    public FreeBotMode Mode;
    public MoveMode MoveMode
    public bool isBaseMode;
    public bool isFreeX;
    public bool isFreeY;
    public bool isFreeZ;
    public bool isFreeRX;
    public bool isFreeRY;
    public bool isFreeRZ;
}
```

Description

[TMcraftShellAPI.FreeBotInfo](#) is a TMcraft class that defines the FreeRobot configuration and is applied by 2 of the [TMcraftShellAPI.RobotStatusProvider](#) functions, [GetFreeBot\(\)](#) and [SetFreeBot\(\)](#). Note that if the member, Mode, is not [FreeBotMode.Custom](#), the rest of the members is meaningless.

Members

Mode	Represents the FreeBot mode; for more detail, please check TMcraft enum FreeBotMode
MoveMode	Represents the Move Mode setting of current Freebot; for more detail, please check TMcraft enum MoveMode .
isBaseMode	True means FreeBot Custom settings being defined by the current base; false means FreeBot Custom settings being defined by the current tool base.
isFreeX	Represents if the FreeBot Custom Setting has freed X axis or not.
isFreeY	Represents if the FreeBot Custom Setting has freed Y axis or not.
isFreeZ	Represents if the FreeBot Custom Setting has freed Z axis or not.
isFreeRX	Represents if the FreeBot Custom Setting has freed Rx axis or not.
isFreeRY	Represents if the FreeBot Custom Setting has freed Ry axis or not.
isFreeRZ	Represents if the FreeBot Custom Setting has freed Rz axis or not.

5.5 TCPInfo

```
public class TCPInfo
{
    public float[] data;
    public string name;
}
```

Description

[TMcraftShellAPI.TCPInfo](#), which describes the basic information of a TCP, is the element type of the Outputs List of [TMcraftShellAPI.TCPProvider.GetTcpList\(\)](#).

Members

data	Tool Center Point, which defines a <code>float[6]</code> {x, y, z, Rx, Ry, Rz} relative to the Flange base.
name	Name of the TCP.

5.6 VariableInfo

```
public class VariableInfo
{
    public string Name;
    public VariableType Type;
    public string value;
    public bool isGlobal;
}
```

Description

`VariableInfo`, paired with `TMcraftShellAPI.VariableProvider` functions such as `GetGlobalVariableList()`, describes all the information of a variable.

Members

Name	Name of the variable.
type	Data type of the variable.
value	Value of the variable.
isGlobal	True if it is a global variable; false if it is a Project Variable.

